



Subject Name:- Operating Systems

Subject Code:- 1BCS304

Faculty Name:- Mrs. Pallavi A R

Designation:- Assistant Professor

COURSE NAME: OPERATING SYSTEMS

CODE: 1BCS304

SEMESTER: 3

MODULE: 1

NUMBER OF HOURS: 09

CONTENTS:

❖ **Introduction to operating systems:**

- What operating systems do?
- Computer System organization
- Computer System architecture
- Operating System structure
- Operating System operations
- Process management
- Memory management
- Storage management

❖ **Operating-System Structures:**

- Operating System Services;
- User - Operating System interface
- System calls
- Types of system calls
- System programs
- Operating system design and implementation
- Operating System structure

MODULE 1

INTRODUCTION TO OPERATING SYSTEM

What is an Operating System?

An operating system is system software that acts as an intermediary between a user of a computer and the computer hardware. It is software that manages the computer hardware and allows the user to execute programs in a convenient and efficient manner.


Operating system goals:

- Make the computer system convenient to use. It hides the difficulty in managing the hardware.
- Use the computer hardware in an efficient manner
- Provide an environment in which user can easily interface with computer.
- It is a resource allocator

Computer System Structure (Components of Computer System)

Computer system mainly consists of four components-

- **Hardware** – provides basic computing resources CPU, memory, I/O devices
- **Operating system** - Controls and coordinates use of hardware among various applications and users
- **Application programs** – define the ways in which the system resources are used to solve the computing problems of the users, Word processors, compilers, web browsers, database systems, video games
- **Users** - People, machines, other computers



List out the User Views and System views of OS

Operating System can be viewed from two viewpoints– User views & System views

User Views: -The user's view of the operating system depends on the type of user.

- If the user is using **standalone** system, then OS is designed for ease of use and high performances. Here resource utilization is not given importance.
- If the users are at different **terminals** connected to a mainframe or minicomputers, by sharing information and resources, then the OS is designed to maximize resource utilization. OS is designed such that the CPU time, memory and i/o are used efficiently and no single user takes more than the resource allotted to them.
- If the users are in **workstations**, connected to networks and servers, then the user have a system unit of their own and shares resources and files with other systems. Here the OS is designed for both ease of use and resource availability (files).
- Other systems like embedded systems used in home device (like washing m/c) & automobiles do not have any user interaction. There are some LEDs to show the status of its work
- Users of **hand-held** systems, expects the OS to be designed for ease of use and performance per amount of battery life


System Views: - Operating system can be viewed as a **resource allocator** and **control program**.

- **Resource allocator** – The OS acts as a manager of hardware and software resources. CPU time, memory space, file-storage space, I/O devices, shared files etc. are the different resources required during execution of a program. There can be conflicting request for these resources by different programs running in same system. The OS assigns the resources to the requesting program depending on the priority.
- **Control Program** – The OS is a control program and manage the execution of user program to prevent errors and improper use of the computer.

Computer System Organization

Computer - system operation

One or more CPUs, device controllers connect through common bus providing access to shared memory. Each device controller is in-charge of a specific type of device. To ensure orderly access to the shared memory, a memory controller is provided whose function is to synchronize access to the memory. The CPU and other devices execute concurrently competing for memory cycles. Concurrent execution of CPUs and devices competing for memory cycles




- When system is switched on, '**Bootstrap**' program is executed. It is the initial program to run in the system. This program is stored in read-only memory (ROM) or in electrically erasable programmable read-only memory (EEPROM).
- It initializes the CPU registers, memory, device controllers and other initial setups. The program also locates and loads the OS kernel to the memory. Then the OS starts with the first process to be executed (ie. 'init' process) and then wait for the interrupt from the user.

Switch on → 'Bootstrap' program

- Initializes the registers, memory and I/O devices
- Locates & loads kernel into memory
- Starts with 'init' process
- Waits for interrupt from user.


Interrupt handling –

- The occurrence of an event is usually signaled by an interrupt. The interrupt can either be from the hardware or the software. Hardware may trigger an interrupt at any time by sending a signal to the CPU. Software triggers an interrupt by executing a special operation called a system call (also called a monitor call).
- When the CPU is interrupted, it stops what it is doing and immediately transfers execution to a fixed location. The fixed location (Interrupt Vector Table) contains the starting address where the service routine for the interrupt is located. After the execution of interrupt service routine, the CPU resumes the interrupted computation.
- Interrupts are an important part of computer architecture. Each computer design has its own interrupt mechanism, but several functions are common. The interrupt must transfer control to the appropriate interrupt service routine



Storage Structure

- Computer programs must be in main memory (**RAM**) to be executed. Main memory is the large memory that the processor can access directly. It commonly is implemented in a semiconductor technology called **dynamic random-access memory (DRAM)**. Computers provide Read Only Memory (ROM), whose data cannot be changed.
- All forms of memory provide an array of memory words. Each word has its own address. Interaction is achieved through a sequence of load or store instructions to specific memory addresses.
- A typical instruction-execution cycle, as executed on a system with a **Von Neumann** architecture, first fetches an instruction from memory and stores that instruction in the **instruction register**. The instruction is then decoded and may cause operands to be fetched from memory and stored in some internal register. After the instruction on the operands has been executed, the result may be stored back in memory.
- Ideally, we want the programs and data to reside in main memory permanently. This arrangement usually is not possible for the following two reasons:
 1. Main memory is usually too small to store all needed programs and data permanently.
 2. Main memory is a *volatile* storage device that loses its contents when power is turned off.
- Thus, most computer systems provide **secondary storage** as an extension of main memory. The main requirement for secondary storage is that it will be able to hold large quantities of data permanently.
- The most common secondary-storage device is a **magnetic disk**, which provides storage for both programs and data. Most programs are stored on a disk until they are loaded into memory. Many programs then use the disk as both a source and a destination of the information for their processing.




- The wide variety of storage systems in a computer system can be organized in a hierarchy as shown in the figure, according to speed, cost and capacity. The higher levels are expensive, but they are fast. As we move down the hierarchy, the cost per bit generally decreases, whereas the access time and the capacity of storage generally increases.
- In addition to differing in speed and cost, the various storage systems are either volatile or nonvolatile. **Volatile storage** loses its contents when the power to the device is

removed. In the absence of expensive battery and generator backup systems, data must be written to **nonvolatile storage** for safekeeping. In the hierarchy shown in figure, the storage systems above the electronic disk are volatile, whereas those below are nonvolatile.

- An **electronic disk** can be designed to be either volatile or nonvolatile. During normal operation, the electronic disk stores data in a large DRAM array, which is volatile. But many electronic-disk devices contain a hidden magnetic hard disk and a battery for backup power. If external power is interrupted, the electronic-disk controller copies the data from RAM to the magnetic disk. Another form of electronic disk is flash memory.

I/O Structure

- A large portion of operating system code is dedicated to managing I/O, both because of its importance to the reliability and performance of a system and because of the varying nature of the devices.
- Every device has a device controller, maintains some local buffer and a set of special- purpose registers. The device controller is responsible for moving the data between the peripheral devices. The operating systems have a **device driver** for each device controller.
- Interrupt-driven I/O is well suited for moving small amounts of data but can produce high overhead when used for bulk data movement such as disk I/O. To solve this problem, direct memory access (DMA) is used.
- After setting up buffers, pointers, and counters for the I/O device, the device controller transfers an entire block of data directly to or from its own buffer storage to memory, with no intervention by the CPU. Only one interrupt is generated per block, to tell the device driver that the operation has completed.



Computer System Architecture

Categorized roughly according to the number of general-purpose processors used.

Single-Processor Systems –

- The variety of single-processor systems range from PDAs through mainframes. On a single-processor system, there is one main CPU capable of executing instructions from user processes. It contains special-purpose processors, in the form of device-specific processors, for devices such as disk, keyboard, and graphics controllers.
- All special-purpose processors run limited instructions and do not run user processes. These are managed by the operating system; the operating system sends them information about their next task and monitors their status.
- For example, a disk-controller processor, implements its own disk queue and scheduling algorithm, thus reducing the task of main CPU. Special processors in the keyboard, converts the keystrokes into codes to be sent to the CPU.
- The use of special-purpose microprocessors is common and does not turn a single-processor system into a multiprocessor. If there is only one general-purpose CPU, then the system is a single-processor system.

Multi-Processor Systems (parallel systems or tightly coupled systems)

Systems that have two or more processors in close communication, sharing the computer bus, the clock, memory, and peripheral devices are the multiprocessor systems.

Multiprocessor systems have three main advantages:


1. *Increased throughput* - In multiprocessor system, as there are multiple processors execution of different programs take place simultaneously. Even if the number of processors is increased the performance cannot be simultaneously increased. This is due to the overhead incurred in keeping all the parts working correctly and also due to the competition for the shared resources. The speed-up ratio with N processors is not N , rather, it is less than N . Thus the speed of the system is not as expected.
2. *Economy of scale* - Multiprocessor systems can cost less than equivalent number of many single-processor systems. As the multiprocessor systems share peripherals, mass storage, and power supplies, the cost of implementing this system is economical. If several processes are working on the same data, the data can also be shared among them.
3. *Increased reliability*- In multiprocessor systems functions are shared among several processors. If one processor fails, the system is not halted, it only slows down. The job of the failed processor is taken up, by other processors.

Two techniques to maintain 'Increased Reliability' - graceful degradation & fault tolerant


1. **Graceful degradation** – As there are multiple processors when one processor fails other process will take up its work and the system go down slowly.
2. **Fault tolerant** – When one processor fails, its operations are stopped, the system failure is then detected, diagnosed, and corrected.

Different types of multiprocessor systems

1. Asymmetric multiprocessing
 2. Symmetric multiprocessing
- 1) *Asymmetric multiprocessing* – (**Master/Slave architecture**) Here each processor is assigned a specific task, by the master processor. A master processor controls the other processors in the system. It schedules and allocates work to the slave processors.
 - 2) *Symmetric multiprocessing (SMP)* – All the processors are considered peers. There is no master-slave relationship. All the processors have their own registers and CPU, only memory is shared.



The benefit of this model is that many processes can run simultaneously. N processes can run if there are N CPUs—without causing a significant deterioration of performance. Operating systems like Windows, Windows XP, Mac OS X, and Linux—now provide support for SMP. A recent trend in CPU design is to include multiple compute **cores** on a single chip. The communication between processors within a chip is faster than communication between two single processors.



Clustered Systems

Clustered systems are two or more individual systems connected together via a network and sharing software resources. Clustering provides high availability of resources and services. The service will continue even if one or more systems in the cluster fail. High availability is generally obtained by storing a copy of files (s/w resources) in the system.

There are two types of Clustered systems – **asymmetric** and **symmetric**

1. *Asymmetric clustering* – one system is in **hot-standby mode** while the others are running the applications. The hot-standby host machine does nothing but monitor the active server. If that server fails, the hot-standby host becomes the active server.

2. *Symmetric clustering* – two or more systems are running applications, and are monitoring each other. This mode is more efficient, as it uses all of the available hardware. If any system fails, its job is taken up by the monitoring system.

Other forms of clusters include parallel clusters and clustering over a wide-area network (WAN). Parallel clusters allow multiple hosts to access the same data on the shared storage. Cluster technology is changing rapidly with the help of **SAN (storage-area networks)**. Using SAN resources can be shared with dozens of systems in a cluster, that are separated by miles.

Operating System Structure

Explain multiprogramming and multitasking systems.

Multiprogramming

One of the most important aspects of operating systems is the ability to multiprogram. A single user cannot keep either the CPU or the I/O devices busy at all times. **Multiprogramming** increases CPU utilization by organizing jobs, so that the CPU always has one to execute.





Fig - Memory layout for a multiprogramming system

- The operating system keeps several jobs in memory simultaneously as shown in figure. This set of jobs is a subset of the jobs kept in the job pool. Since the number of jobs that can be kept simultaneously in memory is usually smaller than the number of jobs that can be kept in the job pool (in secondary memory). The operating system picks and begins to execute one of the jobs in memory. Eventually, the job may have to wait for some tasks, such as an I/O operation, to complete. In a non-multiprogram system, the CPU would sit idle.
- In a multiprogrammed system, the operating system simply switches to, and executes, another job. When *that* job needs to wait, the CPU is switched to *another* job, and so on.
- Eventually, the first job finishes waiting and gets the CPU back. Thus, the CPU is never idle.
- Multiprogrammed systems provide an environment in which the various system resources (for example, CPU, memory, and peripheral devices) are utilized effectively, but they do not provide for user interaction with the computer system.

Multitasking Systems

- In **Time sharing** (or **multitasking**) systems, a single CPU executes multiple jobs by switching among them, but the switches occur so frequently that the users can interact with each program while it is running. The user feels that all the programs are being executed at the same time.
- Time sharing requires an **interactive** (or **hands-on**) **computer system**, which provides direct communication between the user and the system. The user gives instructions to the operating system or to a program directly, using an input device such as a keyboard or a mouse, and waits for immediate results on an output device. Accordingly, the **response time** should be short—typically less than one second.
- A time-shared operating system allows many users to share the computer simultaneously. As the system switches rapidly from one user to the next, each user is given the impression that the entire computer system is dedicated to his use only, even though it is being shared among many users.
- A **multiprocessor system** is a computer system having two or more CPUs within a single computer system, each sharing main memory and peripherals. Multiple programs are executed by multiple processors parallel.



Operating-System Operations

Modern operating systems are **interrupt driven**. If there are no processes to execute, no I/O devices to service, and no users to whom to respond, an operating system will sit quietly, waiting for something to happen. Events are signaled by the occurrence of an interrupt or a trap. A **trap (or an exception)** is a software-generated interrupt. For each type of interrupt, separate segments of code in the operating system determine what action should be taken. An interrupt service routine is provided that is responsible for dealing with the interrupt.

Explain dual mode operation in operating system with a neat block diagram

Dual-Mode Operation

Since the operating system and the user programs share the hardware and software resources of the computer system, it has to be made sure that an error in a user program cannot cause problems to other programs and the Operating System running in the system.

The approach taken is to use a hardware support that allows us to differentiate among various modes of execution.

The system can be assumed to work in two separate **modes** of operation:

1. User mode
2. Kernel mode (supervisor mode, system mode, or privileged mode).

- A hardware bit of the computer, called the **mode bit**, is used to indicate the current mode: kernel (0) or user (1). With the mode bit, we are able to distinguish between a task that is executed by the operating system and one that is executed by the user.
- When the computer system is executing a user application, the system is in user mode. When a user application requests a service from the operating system (via a system call), the transition from user to kernel mode takes place.




Figure Transition from user to kernel mode.

At system boot time, the hardware starts in kernel mode. The operating system is then loaded and starts user applications in user mode. Whenever a trap or interrupt occurs, the hardware switches from user mode to kernel mode (that is, changes the mode bit from 1 to 0). Thus, whenever the operating system gains control of the computer, it is in kernel mode.

The dual mode of operation provides us with the means for protecting the operating system from errant users—and errant users from one another.

- The hardware allows privileged instructions to be executed only in kernel mode. If an attempt is made to execute a privileged instruction in user mode, the hardware does not execute the instruction but rather treats it as illegal and traps it to the operating system. The instruction to switch to user mode is an example of a privileged instruction.
- Initial control is within the operating system, where instructions are executed in kernel mode. When control is given to a user application, the mode is set to user mode. Eventually, control is switched back to the operating system via an interrupt, a trap, or a system call.

Process Management

- A program under execution is a process. A process needs resources like CPU time, memory, files, and I/O devices for its execution. These resources are given to the process when it is created or at run time. When the process terminates, the operating system reclaims the resources.
- The program stored on a disk is a **passive entity** and the program under execution is an **active entity**. A single-threaded process has one **program counter** specifying the next instruction to execute. The CPU executes one instruction of the process after another, until the process completes. A multithreaded process has multiple program counters, each pointing to the next instruction to execute for a given thread.

- The operating system is responsible for the following activities in connection with process management:
 - Scheduling process and threads on the CPU
 - Creating and deleting both user and system processes
 - Suspending and resuming processes
 - Providing mechanisms for process synchronization
 - Providing mechanisms for process communication

Memory Management

Main memory is a large array of words or bytes. Each word or byte has its own address.

Main memory is the storage device which can be easily and directly accessed by the CPU. As the program executes, the central processor reads instructions and also reads and writes data from main memory.

To improve both the utilization of the CPU and the speed of the computer's response to its users, general-purpose computers must keep several programs in memory, creating a need for memory management.

The operating system is responsible for the following activities in connection with memory management:

- Keeping track of which parts of memory are currently being used by user.
- Deciding which processes and data to move into and out of memory.
- Allocating and deallocating memory space as needed.

Storage Management

There are three types of storage management

- i) File system management
- ii) Mass-storage management
- iii) Cache management.

File-System Management

- File management is one of the most visible components of an operating system. Computers can store information on several different types of physical media. Magnetic disk, optical disk, and magnetic tape are the most common. Each of these media has its own characteristics and physical organization. Each medium is controlled by a device, such as a disk drive or tape drive, that also has its own unique characteristics.
- A file is a collection of related information defined by its creator. Commonly, files represent programs and data. Data files may be numeric, alphabetic, alphanumeric, or binary. Files may be free-form (for example, text files), or they may be formatted rigidly (for example, fixed fields).
- The operating system implements the abstract concept of a file by managing mass storage media. Files are normally organized into directories to make them easier to use. When multiple users have access to files, it may be desirable to control by whom and in what ways (read, write, execute) files may be accessed.

The operating system is responsible for the following activities in connection with file management:

- Creating and deleting files
- Creating and deleting directories to organize files
- Supporting primitives for manipulating files and directories
- Mapping files onto secondary storage
- Backing up files on stable (nonvolatile) storage media

Mass-Storage Management

- As the main memory is too small to accommodate all data and programs, and as the data that it holds are erased when power is lost, the computer system must provide secondary storage to back up main memory. Most modern computer systems use disks as the storage medium for both programs and data.
- Most programs—including compilers, assemblers, word processors, editors, and formatters—are stored on a disk until loaded into memory and then use the disk as both the source and destination of their processing. Hence, the proper management of disk storage is of central importance to a computer system.

The operating system is responsible for the following activities in connection with disk management:


- Free-space management
- Storage allocation
- Disk scheduling

As the secondary storage is used frequently, it must be used efficiently. The entire speed of operation of a computer may depend on the speeds of the disk. Magnetic tape drives and their tapes, CD, DVD drives and platters are **tertiary storage** devices. The functions that operating systems provides include mounting and unmounting media in devices, allocating and freeing the devices for exclusive use by processes, and migrating data from secondary to tertiary storage.

Caching

- **Caching** is an important principle of computer systems. Information is normally kept in some storage system (such as main memory). As it is used, it is copied into a faster storage system—the cache—as temporary data. When a particular piece of information is required, first we check whether it is in the cache. If it is, we use the information directly from the cache; if it is not in cache, we use the information from the source, putting a copy in the cache under the assumption that we will need it again soon.
- Because caches have limited size, **cache management** is an important design problem. Careful selection of the cache size and page replacement policy can result in greatly increased performance.
- The movement of information between levels of a storage hierarchy may be either explicit or implicit, depending on the hardware design and the controlling operating-system software. For instance, data transfer from cache to CPU and registers is usually a hardware function, with no operating-system intervention. In contrast, transfer of data from disk to memory is usually controlled by the operating system.

- In a hierarchical storage structure, the same data may appear in different levels of the storage system. For example, suppose to retrieve an integer A from magnetic disk to the processing program. The operation proceeds by first issuing an I/O operation to copy the disk block on which A resides to main memory. This operation is followed by copying A to the cache and to an internal register. Thus, the copy of A appears in several places: on the magnetic disk, in main memory, in the cache, and in an internal register.



- In a multiprocessor environment, in addition to maintaining internal registers, each of the CPUs also contains a local cache. In such an environment, a copy of A may exist simultaneously in several caches. Since the various CPUs can all execute concurrently, any update done to the value of A in one cache is immediately reflected in all other caches where A resides. This situation is called **cache coherency**, and it is usually a hardware problem (handled below the operating-system level).

I/O Systems

One of the purposes of an operating system is to hide the peculiarities of specific hardware devices from the user. The I/O subsystem consists of several components:

- A memory-management component that includes buffering, caching, and spooling
- A general device-driver interface
- Drivers for specific hardware devices


Only the device driver knows the peculiarities of the specific device to which it is assigned.

OPERATING SYSTEM SERVICES

Operating-System Services

Q) List and explain the services provided by OS for the user and efficient operation of system.

An operating system provides an environment for the execution of programs. It provides certain services to programs and to the users of those programs.



OS provide services for the users of the system, including:

- **User Interfaces** - Means by which users can issue commands to the system. Depending on the operating system these may be a **command-line interface** (e.g. sh, csh, ksh, tcsh, etc.), a **Graphical User Interface** (e.g. Windows, X-Windows, KDE, Gnome, etc.), or a **batch command systems**.
In Command Line Interface (CLI)- commands are given to the system.
In Batch interface – commands and directives to control these commands are put in a file and then the file is executed.
In GUI systems- windows with pointing device to get inputs and keyboard to enter the text.
- **Program Execution** - The OS must be able to load a program into RAM, run the program, and terminate the program, either normally or abnormally.
- **I/O Operations** - The OS is responsible for transferring data to and from I/O devices, including keyboards, terminals, printers, and files. For specific devices, special functions are provided (device drivers) by OS.
- **File-System Manipulation** – Programs need to read and write files or directories. The services required to create or delete files, search for a file, list the contents of a file and change the file permissions are provided by OS.

- **Communications** - Inter-process communications, IPC, either between processes running on the same processor, or between processes running on separate processors or separate machines. May be implemented by using the service of OS- like shared memory or message passing.
- **Error Detection** - Both hardware and software errors must be detected and handled appropriately by the OS. Errors may occur in the CPU and memory hardware (such as power failure and memory error), in I/O devices (such as a parity error on tape, a connection failure on a network, or lack of paper in the printer), and in the user program (such as an arithmetic overflow, an attempt to access an illegal memory location).

OS provide services for the efficient operation of the system, including:

- **Resource Allocation** – Resources like CPU cycles, main memory, storage space, and I/O devices must be allocated to multiple users and multiple jobs at the same time.
- **Accounting** – There are services in OS to keep track of system activity and resource usage, either for billing purposes or for statistical record keeping that can be used to optimize future performance.
- **Protection and Security** – The owners of information (file) in multiuser or networked computer system may want to control the use of that information. When several separate processes execute concurrently, one process should not interfere with other or with OS. Protection involves ensuring that all access to system resources is controlled. Security of the system from outsiders must also be done, by means of a password.

User Operating-System Interface

There are several ways for users to interface with the operating system.

- i) Command-line interface, or command interpreter, allows users to directly enter commands to be performed by the operating system.
- ii) Graphical user interface (GUI), allows users to interface with the operating system using pointer device and menu system.

Command Interpreter

- Command Interpreters are used to give commands to the OS. There are multiple command interpreters known as shells. In UNIX and Linux systems, there are several different shells, like the *Bourne shell*, *C shell*, *Bourne-Again shell*, *Korn shell*, and others.
- The main function of the command interpreter is to get and execute the user-specified command. Many of the commands manipulate files: create, delete, list, print, copy, execute, and so on.

The commands can be implemented in two general ways-

- i) The command interpreter itself contains the code to execute the command. For example, a command to delete a file may cause the command interpreter to jump to a particular section of its code that sets up the parameters and makes the appropriate system call.
- ii) The code to implement the command is in a function in a separate file. The interpreter searches for the file and loads it into the memory and executes it by passing the parameter.

Thus by adding new functions new commands can be added easily to the interpreter without disturbing it.


Graphical User Interfaces

- A second strategy for interfacing with the operating system is through a userfriendly graphical user interface or GUI. Rather than having users directly enter commands via a command-line interface, a GUI allows provides a mouse-based window-and-menu system as an interface.
- A GUI provides a **desktop** metaphor where the mouse is moved to position its pointer on images, or **icons**, on the screen (the desktop) that represent programs, files, directories, and system functions.
- Depending on the mouse pointer's location, clicking a button on the mouse can invoke a program, select a file or directory—known as a **folder**— or pull down a menu that contains commands.

System Calls

Q) What are system calls? Briefly point out its types.

- System calls provides an interface to the services of the operating system. These are generally written in C or C++, although some are written in assembly for optimal performance.
- The below figure illustrates the sequence of system calls required to copy a file content from one file (input file) to another file (output file).



An example to illustrate how system calls are used: writing a simple program to read data from one file and copy them to another file

- There are number of system calls used to finish this task. The first system call is to write a message on the screen (monitor). Then to accept the input filename. Then another system call to write message on the screen, then to accept the output filename.

- When the program tries to open the input file, it may find that there is no file of that name or that the file is protected against access. In these cases, the program should print a message on the console (another system call) and then terminate abnormally (another system call) and create a new one (another system call).
- Now that both the files are opened, we enter a loop that reads from the input file (another system call) and writes to output file (another system call).
- Finally, after the entire file is copied, the program may close both files (another system call), write a message to the console or window (system call), and finally terminate normally (final system call).
- Most programmers do not use the low-level system calls directly, but instead use an "Application Programming Interface", API.
- Instead of direct system calls provides for greater program portability between different systems. The API then makes the appropriate system calls through the system call interface, using a system call table to access specific numbered system calls.
- Each system call has a specific numbered system call. The system call table (consisting of system call number and address of the particular service) invokes a particular service routine for a specific system call.
- The caller need know nothing about how the system call is implemented or what it does during execution.




Figure: The handling of a user application invoking the `open()` system call.




Figure: Passing of parameters as a table.

Three general methods used to pass parameters to OS are –

- i) To pass parameters in registers
- ii) If parameters are large blocks, address of block (where parameters are stored in memory) is sent to OS in the register. (Linux & Solaris).
- iii) Parameters can be pushed onto the stack by program and popped off the stack by OS.

Types of System Calls

The system calls can be categorized into six major categories:

1. Process Control
 2. File management
 3. Device management
 4. Information management
 5. Communications
 6. Protection
- Process control
 - end, abort
 - load, execute
 - create process, terminate process
 - get process attributes, set process attributes
 - wait for time
 - wait event, signal event
 - allocate and free memory
 - File management
 - create file, delete file
 - open, close
 - read, write, reposition
 - get file attributes, set file attributes
 - Device management
 - request device, release device
 - read, write, reposition
 - get device attributes, set device attributes
 - logically attach or detach devices
 - Information maintenance
 - get time or date, set time or date
 - get system data, set system data
 - get process, file, or device attributes
 - set process, file, or device attributes
 - Communications
 - create, delete communication connection
 - send, receive messages
 - transfer status information
 - attach or detach remote devices

Figure: Types of system calls

1. Process Control

- Process control system calls include end, abort, load, execute, create process, terminate process, get/set process attributes, wait for time or event, signal event, and allocate and free memory.
- Processes must be created, launched, monitored, paused, resumed, and eventually stopped.
- When one process pauses or stops, then another must be launched or resumed
- Process attributes like process priority, max. allowable execution time etc. are set and retrieved by OS.
- After creating the new process, the parent process may have to wait (wait time), or wait for an event to occur (wait event). The process sends back a signal when the event has occurred (signal event)

2. File Management

The file management functions of OS are –

- File management system calls include create file, delete file, open, close, read, write, reposition, get file attributes, and set file attributes.
- After **creating** a file, the file is **opened**. Data is **read** or **written** to a file.
- The file pointer may need to be **repositioned** to a point.
- The file **attributes** like filename, file type, permissions, etc. are set and retrieved using system calls.
- These operations may also be supported for directories as well as ordinary files.

3. Device Management

- Device management system calls include **request device**, **release device**, **read**, **write**, **reposition**, **get/set** device attributes, and logically **attach** or **detach** devices.
- When a process needs a resource, a request for resource is done. Then the control is granted to the process. If requested resource is already attached to some other process, the requesting process has to wait.
- In multiprogramming systems, after a process uses the device, it has to be returned to OS, so that another process can use the device.
- Devices may be physical (e.g. disk drives), or virtual / abstract (e.g. files, partitions, and RAM disks).

4. Information Maintenance

- Information maintenance system calls include calls to get/set the time, date, system data, and process, file, or device attributes.
- These system calls are used to transfer the information between user and the OS. Information like current time & date, no. of current users, version no. of OS, amount of free memory, disk space etc. are passed from OS to the user.

5. Communication

- Communication system calls create/delete communication connection, send/receive messages, transfer status information, and attach/detach remote devices.
- The **message passing** model must support calls to:
 - Identify a remote process and/or host with which to communicate.
 - Establish a connection between the two processes.
 - Open and close the connection as needed.
 - Transmit messages along the connection.
 - Wait for incoming messages, in either a blocking or non-blocking state.
 - Delete the connection when no longer needed.
- The **shared memory** model must support calls to:
 - Create and access memory that is shared amongst processes (and threads.)
 - Free up shared memory and/or dynamically allocate it as needed.
- Message passing is simpler and easier, (particularly for inter-computer communications), and is generally appropriate for small amounts of data. It is easy to implement, but there are system calls for each read and write process.
- Shared memory is faster, and is generally the better approach where large amounts of data are to be shared. This model is difficult to implement, and it consists of only few system calls.

6. Protection

- Protection provides mechanisms for controlling which users / processes have access to which system resources.
- System calls allow the access mechanisms to be adjusted as needed, and for non- privileged users to be granted elevated access permissions under carefully controlled temporary circumstances.

System Programs

Q) List and explain the different categories of system program?

A collection of programs that provide a convenient environment for program development and execution (other than OS) are called system programs or system utilities.

System programs may be divided into five categories:

1. **File management** - programs to create, delete, copy, rename, print, list, and generally manipulate files and directories.
2. **Status information** - Utilities to check on the date, time, number of users, processes running, data logging, etc. System registries are used to store and recall configuration information for particular applications.
3. **File modification** - e.g. text editors and other tools which can change file contents.
4. **Programming-language support** - E.g. Compilers, linkers, debuggers, profilers, assemblers, library archive management, interpreters for common languages, and support for make.

5. **Program loading and execution** - loaders, dynamic loaders, overlay loaders, etc., as well as interactive debuggers.
6. **Communications** - Programs for providing connectivity between processes and users, including mail, web browsers, remote logins, file transfers, and remote command execution.

Operating-System Design and Implementation

Design Goals

- The first problem in designing a system is to define goals and specifications. At the highest level, the design of the system will be affected by the choice of hardware and the type of system: batch, time shared, single user, multiuser, distributed, real time, or general purpose.
- Beyond this highest design level, the requirements may be much harder to specify. The requirements can, however, be divided into two basic groups
 1. User goals (User requirements)
 2. System goals (system requirements)
- **User requirements** are the features that user care about and understand like system should be convenient to use, easy to learn, reliable, safe and fast.
- **System requirements** are written for the developers, ie. People who design the OS. Their requirements are like easy to design, implement and maintain, flexible, reliable, error free and efficient.

Mechanisms and Policies

- Policies determine *what* is to be done. Mechanisms determine *how* it is to be implemented.
- Example: in timer- counter and decrementing counter is the mechanism and deciding how long the time has to be set is the policies.
- Policies change overtime. In the worst case, each change in policy would require a change in the underlying mechanism.
- If properly separated and implemented, policy changes can be easily adjusted without re- writing the code, just by adjusting parameters or possibly loading new data / configuration files.

Implementation

- Traditionally OS were written in assembly language.
- In recent years, OS are written in C, or C++. Critical sections of code are still written in assembly language.
- The first OS that was not written in assembly language, it was the Master Control Program (MCP).
- The advantages of using a higher-level language for implementing operating systems are: The code can be written faster, more compact, easy to port to other systems and is easier to understand and debug.
- The only disadvantages of implementing an operating system in a higher-level language are reduced speed and increased storage requirements.

Operating-System Structure

Simple Structure

- Many operating systems do not have well-defined structures. They started as small, simple, and limited systems and then grew beyond their original scope. Eg: MS-DOS.
- In MS-DOS, the interfaces and levels of functionality are not well separated. Application programs can access basic I/O routines to write directly to the display and disk drives. Such freedom leaves MS-DOS in bad state and the entire system can crash down when user programs fail.
- UNIX OS consists of two separable parts: the kernel and the system programs. The kernel is further separated into a series of interfaces and device drivers. The kernel provides the file system, CPU scheduling, memory management, and other operating-system functions through system calls.




Figure: MS-DOS layer structure.

Layered Approach

- The OS is broken into number of layers (levels). Each layer rests on the layer below it, and relies on the services provided by the next lower layer.
- Bottom layer (layer 0) is the hardware and the topmost layer is the user interface.
- A typical layer, consists of data structure and routines that can be invoked by higher-level layer.
- Advantage of layered approach is simplicity of construction and debugging.
- The layers are selected so that each uses functions and services of only lower-level layers. So simplifies debugging and system verification. The layers are debugged one by one from the lowest and if any layer doesn't work, then error is due to that layer only, as the lower layers are already debugged. Thus, the design and implementation are simplified.
- A layer need not know how its lower-level layers are implemented. Thus hides the operations from higher layers.





Figure: A layered Operating System

Disadvantages of layered approach:

- The various layers must be appropriately defined, as a layer can use only lower-level layers.
- Less efficient than other types, because any interaction with layer 0 required from top layer. The system call should pass through all the layers and finally to layer 0. This is an overhead.

Microkernels

- This method structures the operating system by removing all nonessential components from the kernel and implementing them as system and user-level programs thus making the kernel as small and efficient as possible.
- The removed services are implemented as system applications.
- Most microkernels provide basic process and memory management, and message passing between other services.
- The main function of the microkernel is to provide a communication facility between the client program and the various services that are also running in user space.



Benefit of microkernel –

- System expansion can also be easier, because it only involves adding more system applications, not rebuilding a new kernel.
- Mach was the first and most widely known microkernel, and now forms a major component of Mac OSX.

Disadvantage of Microkernel -

- Performance overhead of user space to kernel space communication

Modules

- Modern OS development is object-oriented, with a relatively small core kernel and a set of **modules** which can be linked in dynamically.
- Modules are similar to layers in that each subsystem has clearly defined tasks and interfaces, but any module is free to contact any other module, eliminating the problems of going through multiple intermediary layers.
- The kernel is relatively small in this architecture, similar to microkernels, but the kernel does not have to implement message passing since modules are free to contact each other directly. Eg: Solaris, Linux and MacOSX.




Figure: Solaris loadable modules

- The Max OSX architecture relies on the Mach microkernel for basic system management services, and the BSD kernel for additional services. Application services and dynamically loadable modules (kernel extensions) provide the rest of the OS functionality.
- Resembles layered system, but a module can call any other module.
- Resembles microkernel, the primary module has only core functions and the knowledge of how to load and communicate with other modules.